



UIW Print Installation - MAC

This tutorial will walk users through the steps necessary to setup a Mac computer to print to the UIW Print program. In order to connect to the UIW print system, instructions must be completed *while connected* to the UIW wireless or wired network.

Install the PPC Client Software




1. Open the **Finder**
2. Select **Go**
3. Select **Connect to Server**




4. On the Connect to server menu, enter **uiw-sprint1** in the **server address** window and click **Connect**
5. When prompted, click **Connect** again




6. Enter your UIW login credentials (*ad\username and password*) and
7. Choose **Connect** again.
8. *Optional:* Check the **Keychain** checkbox




9. Choose **PCClient** and **Xerox Drivers** from the list of shared folders. *Your view of folders may vary*
10. Click **OK**



11. Choose the **PCClient** tab




12. Double-click the **mac** folder to open it



13. Choose **client-local-install** to install the PCClient application on your mac



14. If you get an error, click **Yes**, and try again. *You will succeed the second time.* When prompted, with the install message below select **Yes**.




15. Enter your **UIW username** and **password** in the window
16. Select **Remember my identity**
17. Click **OK**.




18. The UIW PaperCut Client window will run on the desktop. Your account balance will show in the window.


Install the Xerox Driver package




1. Double-click the **XeroxPrintDriver** icon




2. Double-click the **Xerox Print Driver** icon to install the driver package



3. Click *Continue* and/or *Next* to complete the installation process
4. When you see this screen, click **Continue**




5. On this screen, click **Continue**




6. Click **Close**. The print driver is installed.


Install the Print Anywhere Printer




1. Open **System Preferences**
2. Select **Scanners And Printers**



3. Choose IP, change Protocol to Line Printer Daemon – LPD, and enter uiw-sprint1.ad.uiwtx.edu in Address
4. Enter uiw print anywhere mac in Queue




5. Change *Name window* to read: **Print Anywhere**
6. Click **Select Software**



6. Type Altalink to generate a printer list
7. Choose a **printer** (Xerox Altalink C8045 is recommended)
8. Click **OK**

Printing


1. When you are ready to print, choose **Print Anywhere** from your print queue



2. The first time you print you will need to Login with your *UIW network username and password*
3. Click **OK**.
4. Under *Remember*, select **Always** to keep yourself signed in.
5. Click **OK**
6. The print option re-opens, click **Print**
7. *Go to your nearest printer and swipe your ID to print*

Save PaperCut Client in Startup Folder

In order for UIW Print to work after you restart your Mac you must ensure it is placed in the startup folder.




1. Open **System Preferences**
2. Select **Users and Groups**


3. Click on **Login Items**
4. Click the **plus sign (+)** to add PCClient to the items to open on login


5. Choose **Applications**
6. From the applications list, double-click **PCClient**
7. Click **Add**
8. Close **Users and Groups**


Set Mac Default Print Driver Settings

Open Safari and go to <http://localhost:631/printers>





If you get a message that access is disabled, open a terminal window from spotlight  

 terminal




and enter the following
`cupsctl WebInterface=yes`



Refresh the website. localhost 

Now choose the Printers Tab and then choose the printer you wish to modify.




Click the “Maintenance” dropdown arrow and choose ‘Set Default Options’.




Choose the General tab and change Media Size to Letter (8.5 x 11”)


Output ImageOptions SpecialPages BookletWaterma



Choose the PaperOutput tab.




Scroll down the page until you see 2-Sided Printing and Xerox Back and White fields
Change the 2-Sided Printing dropdown to 2-Sided Print and Xerox Back and White to On as shown.



Choose the Advanced tab and change the XRBannerSheet to Off.

Advanced



Scroll to the bottom of the page and click 'Set Default Options'. Enter admin credentials if prompted.



Open a document, print it, and verify the default settings are '2-Sided Print' and Black and White 'On'.

